

Hystax Acura

Installation Guide (AWS)



Overview

Hystax is a cloud migration and Disaster Recovery company focusing on consistent replication of IT workloads and providing live migration and Best-In-Class Disaster Recovery.

To deploy Hystax Acura solution a customer needs to request Hystax (info@hystax.com) to provide an AMI with the solution and follow the steps described in this document.

Installation requirements

- Amazon Roles: ARN for STS service
- AMI with Hystax Acura (provided by request)
- AMI with Hystax Acura cloud agent. Cloud agent is a service virtual machine responsible for preparing EBS volumes / snapshots and AMIs from migrated machines
- Security groups allowing the following traffic:
 - Hystax Acura host:
 - Ingress – tcp/443
 - Ingress – tcp/4443
 - Ingress – udp/12201
 - Hystax Cloud Agent (spawned automatically in the Target Project):
 - Ingress – tcp/80
 - Ingress – tcp/3260


Installation steps

1. Create a machine from an AMI with Hystax Acura.
2. Open a web browser and go to https://<ip_address> of the machine>/. You will be redirected to the Hystax Setup Wizard. When you complete all the steps, the installation will be done and you can start using Hystax Acura.
3. Step 1 - Fill all the fields on the first step providing cloud configuration details. Please use question mark icons to get hints on the fields. When you click 'Next', the Hystax Setup Wizard will validate the data entered and notify you in case of an error.



Field	Description	Example
AWS access key id	AWS account access key id	AKIAIH2FFMEUAFAOF4A
AWS secret key	AWS account secret key	MkhJX0j7FQ//T0xCUZJtJ3jwZsXAzAddzaszz
Region	AWS region name	us-west-2
Key pair name	Key pair name to access the cloud agent	aws-key
Cloud agent image name	The image from which cloud agent instances will be spun up	ami-06004e6d7b9cda28b
Role ARN	Role ARN for STS service	arn-xxxxxxxxxxxxxxxxxxxxxx
Additional parameters	Other additional parameters in JSON format, for example: {"parameter": "value"}	{"availability_zone": "zone-1"}

- Step 2 – Enter the organization name and Hystax Admin User credentials into the Hystax Setup Wizard. This is the user which you can use to log in to Hystax Acura Control Panel and administer the system. If there are any errors the system will notify you.



hystax

1 — 2 — 3
 Step 1 Step 2 Step 3
 Target cloud configuration Admin user creation Log in


Please provide your organization name and Hystax Control Panel administrator user credentials to created.

Organization*	<input type="text"/>	?
Admin user login (email)*	<input type="text"/>	?
Password*	<input type="password"/>	?
Confirm password*	<input type="password"/>	?

[Next](#)

Contact support: +31 85 888 62 80 | support@hystax.com | [Terms of use](#) | [Help](#)
© 2018 | Hystax | All rights reserved

5. Step 3 – Installation is complete and you can log in to the system using credentials entered on the second step.



hystax

1 — 2 — 3
 Step 1 Step 2 Step 3
 Target cloud configuration Admin user creation Log in

You are all set! Please click the button below to start using Hystax solution.

[Log In](#)

[Next](#)

Contact support: +31 85 888 62 80 | support@hystax.com | [Terms of use](#) | [Help](#)
© 2018 | Hystax | All rights reserved

Troubleshooting

Hystax Acura automatically checks cloud access and necessary permissions for successful operation. It provides detailed error messages describing causes of problems. In case of an error, please check correctness of data entered and necessary permissions.

Use contact details below to reach Hystax support in case you have any questions or problems with the installation process.

Contacts

Email: info@hystax.com

Phone: +31 85 888 62 80

Address: Kingsfordweg 151, Amsterdam, 1043 GR, Netherlands.